

MAX EXTREME V2 SOFTWARE REPROGRAMMING INSTRUCTIONS

IMPORTANT: throughout this procedure the Max MUST be disconnected from the power supply.

- 1) Connect the PicKit 2 programmer to the PC using the supplied USB cable.
- 2) Start your PC and save the new Max software program 'HEX' file (from WON) to your desk top.
- 3) Connect the Max 2 to the programmer via the mini USB socket using the supplied short cable.
- 4) Open up the PIC kit 2 program.
- 5) Click on the 'Auto Import HEX' button near the bottom right.
- 6) Browse to the HEX file saved on the desktop and select it.
- 7) The unit will program and take approx 10 seconds to do so. Once it's finished the display in the top left of the screen will turn green.
- 8) Disconnect the reprogramming cable.